





MRT-1091
SWAK-OS 4.0 Software Update

First step is to make a backup of the v4 database. To do this make sure you are logged into the SWAK software with administrative privileges.


In the top menu bar, select “Management” then “Backup / Restore”.




The backup and restore window should come up. Make sure that the backup radio button is selected. Now select the browse button to open a file explorer window. The backup must be made in the “C:\SQL” folder. For instance, the file path should look like this. C:\SQL\v4 backup 1-16-17.




Next, browse to the “C:\SQL” folder and give your backup a file name that includes the date in the name like v4 backup 1-16-17. Once this has been done, click “Save”.



You will see the “Backup and Restore” window come back up with your save path and file name. Verify it is “C:\SQL\v4 backup 01-16-17.bak” (this is the file name you gave it) and it is saving to the “C:\SQL” folder. If this all looks correct then click the “Execute” button.



If the backup was successful, you will receive a success message. Now click “OK”.




Now that you have made a backup of the v4 database it is time to copy and extract the update package that was download. You should have been sent a link to download the installer package. It is a zip file named “SWAK-OS_4_0_xx.zip” were xx is the revision number. Copy and extract this file to your desktop. Once extracted you will find the following files installer package:

Setup.exe
SwakSetup.msi

To update the SWAK v4 software, run the “Setup.exe” file located in the SWAK-OS_4_0_XX folder then click “Next”.



The installer will install all the needed files to upgrade SWAK v4, then click “Finish”.



Open the software and verify the motion board connects and that the machine homes properly. If you experience any issue, please call Nordson SELECT support.

Customer Service
Nordson SELECT, Inc.
22425 East Appleway Ave
Suite 1
Liberty Lake, WA 99019
Office: +1.509.924.4898
Fax: +1.509.533.1299