



MRT-1076.1S SWAK-OS 4.0 Windows 10 Firewall Settings


1. In Cortana search type "Firewall" and select "Windows Defender Firewall with Advanced Security".




2. Select "Windows Firewall Properties".



3. Select the "Customize" button for protected network connections.



4. Make sure the "Motion Board (Do Not Modify)" network connection is unchecked then click OK. Now repeat this for each of the "Private Profile" and the "Public Profile" tabs.



Customer Service Nordson SELECT, Inc. 22425 E Appleway Ave. Suite 1 Liberty Lake WA, 99019 Office: +1.509.321.5710

Fax: +1.509.533.1299